

This document provides additional assistance with wiring your Extron IP Link Pro Control Processor to your device. Different components may require a different wiring scheme than those listed below.

For complete operating instructions, refer to the user's manual for the specific IP Link Pro Control Processor or the documentation supplied by the manufacturer of the controlled device.

For more information on using Global Scriptor Modules, refer to the "[Guide to Using Scriptor Modules](#)" document.

Device Specifications

Device Type: Video Projector
Manufacturer: Barco
Firmware Version: N/A
Model(s): F90-4K13, F90-W13, F80-Q9

Tested on the Following Software and Firmware Versions

IP Link Pro Control Processor Firmware	Global Scriptor Version
2.06.0002-b002	1.4.2

Version History

Module Version	Date	Notes
1_1_0_0	1/31/2018	Initial Version

Module Notes

- Unidirectional variable must be set to 'True' if status is not required. Default value is 'False'.
Example: InterfaceName.Unidirectional = 'True'
- connectionCounter variable must be set to the number of queries that will be sent to the device before displaying 'Disconnected' if no response is received. Default value is 15.
Example: InterfaceName.connectionCounter = 5

Supported Classes and Examples

SerialClass
InterfaceName = ModuleName.SerialClass(ProcessorName, 'COM1', Model='F90-4K13')
SerialOverEthernetClass
InterfaceName = ModuleName.SerialOverEthernetClass('192.168.254.254', 2001, Model='F90-4K13')
EthernetClass
InterfaceName = ModuleName.EthernetClass('192.168.254.254', 9090, Model='F90-4K13')

Set Commands

Format with Qualifier:

```
InterfaceName.Set(Command, Value, {'Qualifier Key': 'Qualifier Value'})
```

Format without Qualifier:

```
InterfaceName.Set(Command, Value)
```

Command Focus	Value 'In'	Value 'Out'	Value 'Stop'
Qualifier Key 'Steps'	Qualifier Value 1 to 500 in steps of 1		
# Focus example InterfaceName.Set('Focus', 'In', {'Steps': 1})			
Command Illumination	Value 0 to 100 in steps of 1		
# Illumination example InterfaceName.Set('Illumination', 100)			
Command Input	Value 'DVI 1' 'DisplayPort 2' 'SDI'	Value 'DVI 2' 'HDMI'	Value 'DisplayPort 1' 'HDBaseT'
# Input example InterfaceName.Set('Input', 'DVI 1')			
Command LensShift	Value 'Up' 'Right'	Value 'Down' 'Stop'	Value 'Left'
Qualifier Key 'Steps'	Qualifier Value 1 to 500 in steps of 1		
# LensShift example InterfaceName.Set('LensShift', 'Up', {'Steps': 1})			
Command Power	Value 'On'	Value 'Off'	
# Power example InterfaceName.Set('Power', 'On')			
Command Shutter	Value None		
# Shutter example InterfaceName.Set('Shutter', None)			
Command TestPattern	Value 'On'	Value 'Off'	
# TestPattern example			

Global Scripter Module Communication Sheet

InterfaceName.Set('TestPattern', 'On')			
Command TestPatternSelect	Value 'Focus Black' 'Checker Board' 'Monoscope' 'Aspect'	Value 'Ansi Lumen' 'Focus' 'Outline'	Value 'Scenergix' 'Cross Hatch' 'Color Bars'
# TestPatternSelect example InterfaceName.Set('TestPatternSelect', 'Focus Black')			
Command Zoom	Value 'In'	Value 'Out'	Value 'Stop'
Qualifier Key 'Steps'	Qualifier Value 1 to 500 in steps of 1		
# Zoom example InterfaceName.Set('Zoom', 'In', {'Steps': 1})			

Status Available

For all commands, call Update to receive the latest status. ConnectionStatus does not support the Update function and is triggered by the device providing a successful response to other Update function calls.

Format with Qualifier:

```
InterfaceName.Update(Command, {'Qualifier Key': 'Qualifier Value'})
Value = InterfaceName.ReadStatus(Command, {'Qualifier Key': 'Qualifier Value'})
InterfaceName.SubscribeStatus(Command, {'Qualifier Key': 'Qualifier Value'}, FeedbackHandler)
FeedbackHandler will be called only when the specified qualifier gets a new status.
```

Format without Qualifier:

```
InterfaceName.Update(Command)
Value = InterfaceName.ReadStatus(Command)
InterfaceName.SubscribeStatus(Command, None, FeedbackHandler)
FeedbackHandler will be called when any qualifier gets a new status.
```

Command	Value	Value
ConnectionStatus	'Connected'	'Disconnected'
# ConnectionStatus examples Value = InterfaceName.ReadStatus('ConnectionStatus') InterfaceName.SubscribeStatus('ConnectionStatus', None, FeedbackHandler)		
Command	Value	
Illumination	0 to 100 in steps of 1	
# Illumination examples InterfaceName.Update('Illumination') Value = InterfaceName.ReadStatus('Illumination') InterfaceName.SubscribeStatus('Illumination', None, FeedbackHandler)		
Command	Value	Value
Input	'DVI 1'	'DVI 2'
	'DisplayPort 2'	'HDMI'
	'SDI'	'DisplayPort 1'
		'HDBaseT'
# Input examples InterfaceName.Update('Input') Value = InterfaceName.ReadStatus('Input') InterfaceName.SubscribeStatus('Input', None, FeedbackHandler)		
Command	Value	Value
Power	'On'	'Off'
# Power examples InterfaceName.Update('Power') Value = InterfaceName.ReadStatus('Power') InterfaceName.SubscribeStatus('Power', None, FeedbackHandler)		
Command	Value	Value
TestPattern	'On'	'Off'
# TestPattern examples InterfaceName.Update('TestPattern')		

Global Scripter Module Communication Sheet

Value = InterfaceName.ReadStatus('TestPattern') InterfaceName.SubscribeStatus('TestPattern', None, FeedbackHandler)			
Command TestPatternSelect	Value 'Focus Black' 'Checker Board' 'Monoscope' 'Aspect'	Value 'Ansi Lumen' 'Focus' 'Outline'	Value 'Scenergix' 'Cross Hatch' 'Color Bars'
# TestPatternSelect examples InterfaceName.Update('TestPatternSelect') Value = InterfaceName.ReadStatus('TestPatternSelect') InterfaceName.SubscribeStatus('TestPatternSelect', None, FeedbackHandler)			

Cable and Adapter Requirements

Captive Screw to Male DB9 RS-232 Serial Cable

Notes for the Device

Serial communication

Port Type: RS-232

Baud Rate: 19200


Data Bits: 8

Parity: None

Stop Bits: One

Flow Control: None

Pin Assignments Diagram



Signal	Main Cable	Pin	Signal
TxD	→	2	RxD
RxD	←	3	TxD
GND	→	5	GND



Network communication

When configuring the Ethernet module, be sure device settings match those of the Global Scripter ethernet interface

Port Type:	Ethernet
Default Port:	9090
Logon Credentials Supported:	No
Multi-Connection Capabilities:	Undetermined
Port Changeability:	Undetermined

Ethernet Module Configuration Description

Please refer to user manual for settings and changes to the network communication

Notes for the Device

Appendix A. Set Commands

Focus In Steps 1	<code>{"jsonrpc": "2.0", "method": "optics.focus.stepforward", "params": {"steps": 1}, "id": 470}\x0D\x0A</code>
Focus Out Steps 1	<code>{"jsonrpc": "2.0", "method": "optics.focus.stepreverse", "params": {"steps": 1}, "id": 470}\x0D\x0A</code>
Focus Stop Steps 1	<code>{"jsonrpc": "2.0", "method": "optics.focus.stop", "params": {}, "id": 470}\x0D\x0A</code>
Illumination 0	<code>{"jsonrpc": "2.0", "method": "property.set", "id": 300, "params": {"property": "illumination.sources.laser.power", "value": 0}}\x0D\x0A</code>
Illumination 100	<code>{"jsonrpc": "2.0", "method": "property.set", "id": 300, "params": {"property": "illumination.sources.laser.power", "value": 100}}\x0D\x0A</code>
Input DVI 1	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "DVI 1"}, "id": 423}\x0D\x0A</code>
Input DVI 2	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "DVI 2"}, "id": 423}\x0D\x0A</code>
Input DisplayPort 1	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "DisplayPort 1"}, "id": 423}\x0D\x0A</code>
Input DisplayPort 2	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "DisplayPort 2"}, "id": 423}\x0D\x0A</code>
Input HDBaseT	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "HDBaseT"}, "id": 423}\x0D\x0A</code>
Input HDMI	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "HDMI"}, "id": 423}\x0D\x0A</code>
Input SDI	<code>{"jsonrpc": "2.0", "method": "property.set", "params": {"property": "image.window.main.source", "value": "SDI"}, "id": 423}\x0D\x0A</code>
Lens Shift Down Steps	<code>{"jsonrpc": "2.0", "method": "optics.lensshift.vertical.stepforward", "params": {"steps": 1}, "id": 2356}\x0D\x0A</code>

Global Scripter Module Communication Sheet

Revision: 1/31/2018

Lens Shift Left Steps 1	{"jsonrpc": "2.0", "method": "optics.lensshift.horizontal.stepreverse", "params": {"steps": 1}, "id": 2356}\x0D\x0A
Lens Shift Right Steps 1	{"jsonrpc": "2.0", "method": "optics.lensshift.horizontal.stepforward", "params": {"steps": 1}, "id": 2356}\x0D\x0A
Lens Shift Stop Steps 1	{"jsonrpc": "2.0", "method": "optics.lensshift.stop", "params": {}, "id": 2356}\x0D\x0A
Lens Shift Up Steps 1	{"jsonrpc": "2.0", "method": "optics.lensshift.vertical.stepreverse", "params": {"steps": 1}, "id": 2356}\x0D\x0A
Power Off	{"jsonrpc": "2.0", "method": "system.poweroff", "params": {}, "id": 130}\x0D\x0A
Power On	{"jsonrpc": "2.0", "method": "system.poweron", "params": {}, "id": 130}\x0D\x0A
Shutter None	{"jsonrpc": "2.0", "method": "optics.shutter.toggle", "params": {}, "id": 310}\x0D\x0A
Test Pattern Off	{"jsonrpc": "2.0", "method": "property.set", "id": 141, "params": {"property": "image.testpattern.show", "value": false}}\x0D\x0A
Test Pattern On	{"jsonrpc": "2.0", "method": "property.set", "id": 141, "params": {"property": "image.testpattern.show", "value": true}}\x0D\x0A
Test Pattern Select Ansi Lumen	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Ansi Lumen"}}\x0D\x0A
Test Pattern Select Aspect	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Aspect"}}\x0D\x0A
Test Pattern Select Checker Board	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Checker Board"}}\x0D\x0A
Test Pattern Select Color Bars	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Color Bars"}}\x0D\x0A
Test Pattern Select Cross Hatch	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Cross Hatch"}}\x0D\x0A
Test Pattern Select Focus	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Focus"}}\x0D\x0A
Test Pattern Select Focus Black	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property":

Global Scripter Module Communication Sheet

Revision: 1/31/2018

	"image.testpattern.selected", "value": "internal:Focus Black"}}\x0D\x0A
Test Pattern Select Monoscope	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Monoscope"}}\x0D\x0A
Test Pattern Select Outline	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Outline"}}\x0D\x0A
Test Pattern Select Scenergix	{"jsonrpc": "2.0", "method": "property.set", "id": 147, "params": {"property": "image.testpattern.selected", "value": "internal:Scenergix"}}\x0D\x0A
Zoom In Steps 1	{"jsonrpc": "2.0", "method": "optics.zoom.stepforward", "params": {"steps": 1}, "id": 450}
Zoom Out Steps 1	{"jsonrpc": "2.0", "method": "optics.zoom.stepreverse", "params": {"steps": 1}, "id": 450}
Zoom Stop Steps 1	{"jsonrpc": "2.0", "method": "optics.zoom.stop", "params": {}, "id": 450}\x0D\x0A

Appendix B. Update Commands

Illumination	<code>{"jsonrpc": "2.0", "method": "property.get", "params": {"property": "illumination.sources.laser.power"}, "id": 300}\x0D\x0A</code>
Input	<code>{"jsonrpc": "2.0", "method": "property.get", "params": {"property": "image.window.main.source"}, "id": 423}\x0D\x0A</code>
Power	<code>{"jsonrpc": "2.0", "method": "property.get", "params": {"property": "system.state"}, "id": 130}\x0D\x0A</code>
Test Pattern Select	<code>{"jsonrpc": "2.0", "method": "property.get", "params": {"property": "image.testpattern.selected"}, "id": 147}\x0D\x0A</code>